


DC Agent 如何手动设置连接打印机

启动 / 配置


成功安装后，软件在右下角任务栏：




鼠标右键 DC Agent 图标，选择“配置”：



主界面 - 设备 - 编辑:



点击“手动添加”:



[Wi-Fi 连接模式]

连接： 网络连接设备

类型： IP 地址

设备 ID： 输入“打印机 IP”



The image shows a dialog box titled "设备列表" (Device List) with a close button (X) in the top right corner. Inside the dialog, there are three configuration fields: "连接" (Connection) set to "网络连接设备" (Network connection device), "类型" (Type) set to "IP 地址" (IP address), and "设备 ID" (Device ID) with an empty text input field. At the bottom, there are two buttons: "确定" (OK) and "取消" (Cancel).

注： 可使用驱动安装向导配置 Wi-Fi 连接，具体方法请参考打印机用户指南。


[USB 连接模式]

连接： USB 连接设备

类型： 主机名

设备 ID： 电脑 IP


出厂编号： 打印机序列号



The image shows a dialog box titled "设备列表" (Device List) with a close button (X) in the top right corner. Inside the dialog, there are four configuration fields: "连接" (Connection) set to "USB 连接设备" (USB connection device), "类型" (Type) set to "主机名" (Host name), "设备 ID" (Device ID) with an empty text input field, and "出厂编号" (Factory number) with an empty text input field. At the bottom, there are two buttons: "确定" (OK) and "取消" (Cancel).

验证

鼠标右键电脑右下角任务栏里的图标，点击“立即获取设备信息”：




成功示例：



如获取以上数据，则说明数据采集成功，点击“继续”发送数据。

注：发送数据时，请确保电脑处于联网状态。

若打印机数据获取成功，但发送数据失败：



请检查网络配置或参考《DC Agent 代理设置说明》